

DSRF Flat File Library and Conformance Tool

User manual

Last updated: May 2019

License: [Open source - Apache 2](#)

Git repo: <https://github.com/ddexnet/dsrf>

[Introduction](#)

[Installation](#)

[Requirements](#)

[Step-by-step guide](#)

[Testing your installation](#)

[Directory Structure](#)

[Running DSRF](#)

[The conformance tool](#)

[Executing a custom script](#)

[Appendix: Installing the google Protocol buffer compiler](#)

[Instructions for Windows OS](#)

[Instructions for MAC OS X](#)

[Instructions for LINUX](#)

Introduction

The *DSRF Flat File Parser and Conformance Tool* is a open source Library that allows you to parse and test DDEX DSR Flat files in conformance with [DDEX DSR Flat File Standard v3.0](#).

Installation

The Library can be installed on the following platforms:

- Mac OS X
- Linux
- Windows

Requirements

Prior to installation you will need the following packages

- Python (preferably v2.7 although other versions might work).
- Google Protocol Buffer compiler.

To verify that both of these are installed and accessible, you should be able to run both of these commands from the command line without getting a "command not found":

```
$ python --version
Python 2.7.10

$ protoc --version
libprotoc 3.6.1
```

If you need to install python or Google Protocol Buffer see Annex below for detailed instructions.

Step-by-step guide

1. Download and decompress the DSRF install package (dsrf_1_0_x.tar)
2. From a Terminal, run the following command

For Unix (Mac OS X or Linux):

```
$ sudo python setup.py install
```

For Windows:

Open your command line as Administrator (right-click on cmd.exe):

```
$ python setup.py install
```

Upon successful installation, you should read the following message:

```
Installed /Library/Python/2.7/site-packages/dsrf-1.0.0-py2.7.egg
Processing dependencies for dsrf==1.0.1 1
Finished processing dependencies for dsrf==1.0.1
```

Testing your installation

Run the following commands from a Terminal:

```
$ TEST_FILE=testdata/DSR_TEST_YouTube_AdSupport-music_2015-Q4_IS_1of1_20160121T150926.tsv
$ python run_dsrf.py $TEST_FILE --human_readable=True
```

Note: in all the following examples, we will replace the filename by this variable. Make sure you assign it a value or replace the variable name by an existing filename.

You should see the report displayed as human readable protocol buffer starting with:

```
type: HEAD
version: "dsrf/30"
file_number: 1
rows {...
```

If that's the case. Congratulations ! your DSRF parser is now ready to run.

Directory Structure

Your newly created directory should look like this

```
dsrf/
├── conformance/
├── parsers/
├── processor/
├── proto/
├── revenue_example/
├── schemas/
└── testdata/
```

conformance:

Contains the script that verify that your file is conformant to the specified Profile in the Standard. The output is in the specified log file.

parsers:

Contains the scripts that parse the files and extract the blocks to create the proto buffers queue.

processor:

Contains the scripts that process the reports

proto:

Contains the schema of the protocol buffers. Those files should NOT be edited.

revenue_example:

Contains example of scripts to be executed by the DSRF parser. You may use these example to create your own scripts.

schemas:

Contains the XSD files that represent (a) the allowed values for specific fields in the Standard and (b) the schema of all the profiles. Those files should NOT be edited.

testdata:

Contains the sample reports and the test files.

Running DSRF

The DSRF parser is executed with the following syntax:

```
$ python run_dsrf.py [-h] [--dsrf_xsd_file DSRF_XSD_FILE]
[--avs_xsd_file AVS_XSD_FILE] [--dsrf_version DSRF_VERSION]
[--log_file LOG_FILE] [--human_readable HUMAN_READABLE] files_list
[files_list ...] | python [script] [--profile_name PROFILE]
```

Explanation of the variables:

--help	print this help message and exit
--dsrf_xsd_file	The dsrf xsd schema file. This file contains the profiles and the row types definition. The default value is : 'schemas/3.0/sales-reporting-flat.xsd'
--avs_xsd_file	The xsd avs schema file. This file contains the allowed value set to the fixed string cells. The default value is : 'schemas/3.0/avs.xsd'
--dsrf_version	The format version The default value is : '3.0'

--log_file	This file will contain the library logs. The default value is ' <i>\$tmp/example.log</i> ' where <i>\$tmp</i> is your system's default tmp directory . You can also specify a custom log file location.
--human_readable	If True, write the block to the stdout in human readable form. The default value is 'False'.
files_list	List of the files to be processed. Filenames are separated by a space character. For multi-file reports, all the files must be listed. 3 Compressed files are supported.
script	Name of the script you want to execute. This script takes the parsed blocks as input. For conformance validation, use <code>conformance/conformance_processor.py</code> .
--profile_name	The name of the profile you want use for validation (if you're using the <code>conformance_processor.py</code> script above). Allowed values are dictated by the XSD (eg. "UgcProfile" and "BasicAudio").

The conformance tool

To check whether a file is conformant with the DSRF Standard, run the following command:

```
$ python run_dsrf.py --log_file=example.log $TEST_FILE | python
conformance/conformance_processor.py --profile_name=UgcProfile
```

The output should be as follows:

```
[Block conformance] Blocks validated: X blocks(Y rows).
The conformance validation passed successfully! Validated X blocks (Y
rows).
And your log file should look like this
INFO:dsrf.parsers.dsrf_report_manager:Validating the report file names.
INFO:dsrf.parsers.dsrf_report_manager:Start parsing file number 1.
INFO:dsrf.parsers.dsrf_report_manager:Start parsing the HEAD block in file number 1.
INFO:dsrf.parsers.dsrf_report_manager:Start parsing block number 1 in file number 1.
INFO:dsrf.parsers.dsrf_report_manager:Start parsing block number 2 in file number 1.
INFO:dsrf.parsers.dsrf_report_manager:Start parsing block number 3 in file number 1.
INFO:dsrf.parsers.dsrf_report_manager:Start parsing the FOOT block in file number 1.
```

Executing a custom script

The library includes a sample of a custom script, which you can execute as follows:

```
>$ python run_dsrf.py $TEST_FILE | python  
revenue_example/revenue_processors.py PUB_3
```

The name of a RightsController (PUB_3 in this example) must be passed as an argument. The script will return the sum of the Revenue attributed to PUB_3 in each block of the report. You can use this script as a base to extract any value or aggregate values from the report.

Appendix: Installing the google Protocol buffer compiler

The instructions below assumes that you have Python installed. If that is not the case, please follow the instructions at <https://www.python.org/downloads>.

Instructions for Windows OS

- Download the protocol buffer compiler from <https://github.com/google/protobuf/releases>. Choose the Windows version : **protoc-3.0.0-beta-2-win32.zip**
Unzip and copy the directory somewhere under you /ProgramFiles directory (eg. c:\Program Files\DSRF_Library\protoc-3.0.0-beta-2-win32\protoc.exe)
You need to declare the Path to the compiler :
Open your command line as Administrator (right-click on cmd.exe)

```
> set PATH=%PATH%;c:\Program  
Files\DSRF_Library\protoc-3.0.0-beta-2-win32
```

- You will also need the Python runtime library from <https://github.com/google/protobuf>
Download unzip [master.zip](#)
Open your command line as Administrator (right-click on cmd.exe)
Go to the \python directory

```
> python setup.py
```

To test your installation, from your command line you should get the following:

```
> python --version
python 2.7.xx
> protoc --version
Libprotoc 3.0.0
```

Instructions for MAC OS X

- Download the protocol buffer compiler from <https://github.com/google/protobuf/releases>. Choose the OS X version : [protoc-3.0.0-beta-2-osx-x86_32.zip](#)
Unzip and copy the protoc executable somewhere in your system PATH, eg:

```
$ sudo cp path/to/protoc /usr/local/bin/
```

- You will also need the Protobuf Python runtime library from <https://github.com/google/protobuf>
Download and unzip [master.zip](#)

Fro the python/ directory, run:

```
$ sudo python setup.py
```

- To test your installation, from your command line you should get the following:

```
$ python --version
python 2.7.xx
$ protoc --version
Libprotoc 3.0.0
```

Instructions for LINUX

On Linux, you can install the protobuf compiler using the Advanced Package Tool:

```
$ sudo apt-get update
$ sudo apt-get install protobuf-compiler
```

To test your installation, from your command line you should get the following:

```
$ python --version
python 2.7.xx
$ protoc --version
Libprotoc 3.0.0
```